

show version

…ルータのいろいろな情報を表示 [ショウバージョン]

<利用方法>

IOSバージョン、実装メモリ(DRAM、Flash)、起動時間などの確認

<実行例>

```
Router#sh ver
Cisco Internetwork Operating System Software
IOS (tm) C2600 Software (C2600-I-M), Version 12.0(4)T,  RELEASE SOFTWARE (fc1)
Copyright (c) 1986-1999 by cisco Systems, Inc.
Compiled Wed 28-Apr-99 16:50 by kpma
Image text-base: 0x80008088, data-base: 0x806B44EC

ROM: System Bootstrap, Version 11.3(2)XA3, PLATFORM SPECIFIC RELEASE SOFTWARE (f
c1)

Router uptime is 2 hours, 12 minutes
System restarted by power-on at 13:49:46 JPT Sun May 22 2005
System image file is "flash:c2600-i-mz.120-4.T.bin"

cisco 2610 (MPC860) processor (revision 0x202) with 18432K/6144K bytes of memory
.
Processor board ID JAB023502KG (4104375789)
M860 processor: part number 0, mask 49
Bridging software.
X.25 software, Version 3.0.0.
1 Ethernet/IEEE 802.3 interface(s)
16 terminal line(s)
32K bytes of non-volatile configuration memory.
8192K bytes of processor board System flash (Read/Write)

Configuration register is 0x2102
```

<補足>

実務で最も使用するコマンドのひとつである。上記ルータの場合、IOSバージョンは12.0(4)T、起動後2時間12分経過している、実装DRAMメモリは24MB、実装flashメモリは8MBである。(DRAMメモリは丸で囲った部分の数値を足して算出する。)